Coat "Sally" Model 120-10 Sizes 36-48





PRINT THE CUT

- 1. Open the pattern PDF and set the control square to Page 1 with the setting "Original size" on DIN Print A4 paper (do not click on "Adjustment to page size"!)
- 2. Check the square if it is 10 x 10 cm, print out the whole cut sheet.
- 3. Place all pages next to each other as indicated by the arrows and adhere them row by row along the boundary lines, then glue the rows together.
- 4. Compare the body measurements with the table measurements and cut out the cut parts in the appropriate size (the overview of the cut parts is on the pattern sheet). Important: Instructions do not include seam allowances, unless otherwise indicated.

SUPPLIES

- 2.6–3.4 m suede imitation, stone-coloured, 145 cm wide
- Vlieseline G 785 or LE 420 (Vlieseline)
- 1 press button, 20 mm in diameter (Union Knopf) Optional BERNINA accessories
- Walking foot 50

CUTTING

Cut front and back part one from the other at the dividing line.

- 1 $2 \times$ upper front part
- 1 $2 \times$ lower front part
- $2 \times facing of the front part$
- 3 $1 \times$ upper back part on the fold
- 3 $1 \times$ lower back part on the fold
- 3 $1 \times$ rear facing on the fold
- 4 $1 \times$ hem facing on the fold
- 5 2 x sleeve facing
- 6 $1 \times$ upper collar on the fold

7 $1 \times lower collar on the fold$

Pocket approx. 17×17 cm. Pocket facing approx. 17×5 cm.

INSTRUCTIONS

- 1. If desired, iron the stabiliser carefully and not too hot on all facings and the lower collar.
- Sew the upper edge of the pocket on the pocket facing. Place the pocket right side on right side on the facing and sew along the sides. Sew the pocket with the allowances folded back on the right lower front part.
- 3. Close the dividing seams on the front and back part. Fold the allowances apart and topstitch them. Close the shoulder seams on the coat and the facings. Fold the allowances in the coat to the back part and topstitch them. Close the sleeve and side seams.
- 4. For sewing the lapel collar, refer to <u>Tips in Inspiration 1/20</u>. In doing so, sew the hem facings of the outer edges right side on right side on the front facings before turning them over. Fold down the lapel, fix the facing with pins and topstitch the layers, if necessary, along the marked line.
- 5. Close the sleeve facings to a ring and sew them on in the same way as the hem facing. Topstitch the upper edges of the hem and sleeve facings.
- 6. Attach the press button. Topstitch the facing in the seam shadow of the dividing seam at a distance of approx. 5 cm from the edge.









LAPEL COLLAR

USING THE EXAMPLE OF THE BLAZER, WE WOULD LIKE TO SHOW YOU HOW TO SEW A LAPEL COLLAR.

When following our picture series, please be aware that due to the firm material and the intended softer drape, we decided not to use any stabiliser in the lapel facing.

Note: For light or fraying fabrics, iron a small piece of stabiliser on the inside corners on the front part and the facing (illustration 1, below).

- 1. Topstitch the lower collar along the neckline of the coat, symbol heart to heart, leaving the seam allowances open at the ends.
- 2./3. Clip the allowance in the inside corners up to the seam line, sew the short edges from heart to cross. Iron the allowances apart.
 - Sew the upper collar to the neckline of the facings, symbol star to star, clip the corners of the facing as described above. Sew on the short edges from star to hexagon. Iron the allowances apart.
- 4. Sew the outer collar edges together right side on right side, gathering the excess length of the upper collar.
- 5. Cut back the allowances in layers and clip in the curves.
- 6. Sew the outer edges of the jacket and facings together. Clip the allowances along the curves and cut the corners back. If the collar and the front edge are not to be topstitched at the outer edges, the allowances on the collar can be placed in the lower collar and topstitched as far as possible. This results in a better drape of the edges. The allowances on the upper lapel are placed in the coat and topstitched to about 5 cm above the dividing seam. 5 cm below the lapel fold, place the allowances in the facings and topstitch as well.


Turn the facing inwards. At the base of the collar, pin seam to seam. Sew the first seam (heart to heart) from the right in seam shadow. Topstitch the collar and the front edge as desired.

Tip: In order to sew the facing on the front part along the hem, the corner is sewn on the sewing line and the long edge of facing is pulled slightly down to sew it on the hem of the jacket. See the inside and outside view in the illustration (illustration 2 and 3).






















Illustration 2

Illustration 3